Übertragen einer Netzwerklizenz auf einen anderen Rechner

Kopieren Sie die Dateien "haspdinst.exe" und "Rus.exe" aus dem SigmaPlot 13-Programmverzeichnis oder aus dem "License Manager"-Verzeichnis der Installations-CD auf den Ziel-Rechner, auf den Sie die Netzwerklizenz übertragen wollen. Installieren Sie den Lizenzmanager auf dem neuen Rechner. Auf beiden Rechnern, dem bisherigen und dem neuen Lizenzserver, muß der Lizenzmanager-Dienst installiert sein.

1

Starten Sie (mit Administrator-Rechten) auf dem Ziel-Rechner das Programm RUS.exe, und wählen Sie den "Transfer License"-Tab.

collect Status Information Ap	ply License File	Transfer Lice	nse		
transfer (rehost) a license from o nputers. On each computer, selec	ne computer to an t the Transfer Li	other, you run cense tab an	the RUS p d perform	program of the appro-	on both opriate step
Collect information about the re-	opient computer				
Step 1: On the computer to whi collect and save information abo	ch you want to tra out the computer.	nsfer the licen	se (the "re	cipient co	mputer"),
Save recipient information to $\widetilde{ / }$	apps/SPW13_Netv	vork_License_	Assistance	/fie1.id	- are
			Collect an	d Save In	formation
Generate the license transfer file					
Generate the license transfer fli Step 2: On the computer that o the license to transfer, read the	e rrently contains the recipient information of the second	ne license (the on file and ger	"source co terate a lic	omputer") Sense tran	, select isfer file.
Generate the license transfer file Step 2: On the computer that or the license to transfer, read the Key Type Key II	t irrently contains th recipient informati D	ne license (the on file and ger Products	"source co nerate a lic	omputer") Sense trar), select rsfer file.
Generate the license transfer file Step 2: On the computer that or the license to transfer, read the Key Type Key II	e urrently contains ti recipient informati D	ne icense (the on file and ger Products	"source co terate a lic	omputer") iense trar	, select isfer file.
Generate the license transfer file Step 2: On the computer that of the license to transfer, read the Key Type Key II	e urrently contains ti recipient informati D	ne license (the on file and ger Products	"source co terate a lic	omputer") Jense trar	, select Infer file.
Generate the license transfer fil Step 2: On the computer that or the license to transfer, read the Key Type Key II	e urrently contains th recipient informati D	te license (the on file and ger Products	"source co terate a lic	omputer") iense trar	, select isfer file.
Generate the license transfer flik Step 2: On the computer that of the license to transfer, read the Key Type Key II	e urrently contains th recipient informati D	ne license (the on file and ger Products	"source co erate a lic	omputer") ense tra	, select rsfer file.
Generate the license transfer fli Step 2: On the computer that o the license to transfer, read the Key Type Key II Read the recipient information f	e rrecipient informati D	ne license (the on file and ger Products	"source or rerate a lic	omputer") sense tran	, select rsfer file.
Generate the license transfer fla Step 2: On the computer that of the license to transfer, read the Key Type Key II Read the recipient information fi Generate the license transfer fil	e urrently contains the recipient information D	ne license (the on file and gen Products	"source or rerate a lic	omputer") sense tran	, select isfer file.

Geben Sie im Feld "Save recipient information to field" Dateiname und –ort ein, und klicken Sie auf den "Collect and Save Information"-Button. Das erzeugt eine "*.id"-Datei für den Zielrechner. Diese Datei wird später zum Übernehmen der Netzwerklizenz verwendet.



Klicken Sie auf OK, um die Identifikationsdatei für den Zielrechner zu erzeugen. Kopieren Sie die Datei auf den Rechner, auf dem die Lizenz bisher besteht, oder sorgen Sie dafür, daß die Datei im Netzwerk erreichbar ist.

Starten Sie auf dem Rechner, auf dem die Lizenz bisher besteht ("Quellrechner") die Datei RUS.exe, mit Administrator-Rechten. Wählen Sie den "Transfer License"-Tab.

Collect Status Information Apply Lice	ense File Transfer License	
transfer (rehost) a license from one con mputers. On each computer, select the 1	nputer to another, you run the RUS program of Fransfer License tab and perform the appro-	on both opriate ster
Collect information about the recipient	computer	
Step 1: On the computer to which you collect and save information about the	want to transfer the license (the "recipient co computer.	mputer"),
Save recipient information to		
	Collect and Save In	formation
Consiste the Icense transfer Re		
Generate the license transfer file		
Generate the license transfer file Step 2: On the computer that currently the license to transfer, read the recipie	y contains the license (the "source computer") Int information file and generate a license tra	, select
Generate the license transfer file Step 2: On the computer that currently the license to transfer, read the recipie Key Type Key ID	y contains the license (the "source computer") Int information file and generate a license tran Products	, select Insfer file.
Generate the license transfer file Step 2: On the computer that currently the license to transfer, read the recipie Key Type Key ID	y contains the license (the "source computer") int information file and generate a license tran Products), select rsfer file.
Generate the license transfer file Step 2: On the computer that currently the license to transfer, read the recipie Key Type Key ID	y contains the license (the "source computer") Int information file and generate a license tran Products	, select Insfer file.
Generate the license transfer file Step 2: On the computer that currently the license to transfer, read the recipie Key Type Key ID	y contains the license (the "source computer") Int information file and generate a license tran Products	, select isfer file,
Generate the license transfer file Step 2: On the computer that currently the license to transfer, read the recipie Key Type Key ID	y contains the license (the "source computer") int information file and generate a license tra Products	, select isfer flie.
Generate the license transfer file Step 2: On the computer that currently the license to transfer, read the recipie Key Type Key ID	y contains the license (the "source computer") Int information file and generate a license tra Products	i, select Isfer file.
Generate the license transfer file Step 2: On the computer that currently the license to transfer, read the recipie Key Type Key ID	y contains the license (the "source computer") int information file and generate a license tra Products	i, select isfer file.
Generate the license transfer file Step 2: On the computer that currently the license to transfer, read the recipie Key Type Key ID Read the recipient information file from	y contains the license (the "source computer") int information file and generate a license tran Products 9 roducts	, select isfer file.
Generate the license transfer file Step 2: On the computer that currently the license to transfer, read the recipie Key Type Key ID Read the recipient information file from	v contains the license (the "source computer") int information file and generate a license tran Products 1 W13_Network_License_Assistance/file1.id	, select rsfer file.
Generate the license transfer file Step 2: On the computer that currently the license to transfer, read the recipie Key Type Key ID Read the recipient information file from Generate the license transfer file to	v contains the license (the "source computer") int information file and generate a license tra Products W13_Network_License_Assistance/file1.id Network SPW13_Installation_files/file.h2h	, select rsfer file.

Im Feld "Read the recipient information file from" wählen Sie die ".id"-Datei, die Sie auf dem Zielrechner erzeugt haben.

Geben Sie dann im Feld "Generate the license transfer file to" Name und Ort der Transfer-Datei ein, in die die Lizenz übertragen werde soll. Klicken Sie auf den "Generate License Transfer File"-Button, um die Transfer-Datei mit der Endung ".h2h" zu erzeugen

3

Diese Datei ist die neue Lizenzdatei, die Sie auf dem Zielrechner installieren können. Starten Sie dort den Lizenzmanager, und lesen Sie die Lizenz(en) ein.